

pilar

since v. 2024.3

PILAR
car file

José A. Mañas <jmanas@pilar-tools.com>

October, 2024



- CAR (configuration) file
- it is a text file: you may edit it
- it establishes language,
 - threats profiles (TSV),
 - security profiles (EVL)
 - ...



car based on car

- if there is a CAR file that
 - is quite adequate for you but incomplete
 - is in a read-only directory
 - ...
- then you can use your own car file that references the other one
 - “this/” prefix is used to refer to the directory where the file is

```
$ cat MyCIS_en.car  
  
base_car= C:/Program Files (x86)/PILAR_7.4/CIS_en.car  
  
tsv= this/MyTSV.xlsx  
  
profile= this/ISOIEC 27017 20190712_en.evl  
  
reports= this/MyReports.xml
```



threat profiles

- TSV – Threat Standard Values
- add tsv
 - e.g.: tsv= this/MyTSV.xlsx
- tsv entries are usually aggregated to the previous ones
- you may need to remove old entries before adding new ones
 - XML
 - <reset />
 - <reset F="family-code" />
 - excel

car files

	A	B	C	D	E
1	app	family	threat	likely	D=en:PD
1	app	family	threat		
2	no				
3	reset				
4	opt	essential.info.per	PR.ex.aepd.p1		
5	opt	essential.info.per	PR.ex.aepd.p1		

	A	B	C	D	E
1	app	family	threat	likely	D=en:PD
1	app	family	threat	likely	D=en:PD
2	no				personal data
3	reset	essential.info.per			
4	opt	essential.info.per	PR.ex.aepd.p1.1	1	10%
5	opt	essential.info.per	PR.ex.aepd.p1.2	1	10%



security profiles

- EVL – evaluation lists
- add new profile
 - e.g.: from BIB file
profile= bib_en/27002_2005_2014-04-01_en.evl
 - e.g.: from this file
profile= this/ISOIEC 27017 20190712_en.evl



- Report templates
- add
 - e.g.: reports= this/mydirectory/[index.xml]
 - e.g.: reports= this/mydirectory/reports.xml
- replace
 - in the XML file, include a reset tag
<reset />
- Note
 - internal paths (in file.xml) are always relative to xml-file path



database parameters

- default parameters for db connections

```
template=jdbc:mariadb://database_server/database_name  
jar=C:\pkt\dbms\mariadb-java-client-2.7.3.jar  
class=org.mariadb.jdbc.Driver  
server=10.76.186.39:3306  
name=test
```

P

any question?



support@pilar-tools.com